





Class 1 prep Tooth #30

Tooth	What to do	Notes
	<p>Check you are on the correct Tooth...</p>	<p>Drill on wrong tooth (autofail)</p>
	<p>34 D Bur</p> <p>Drill pits</p>	<p>Depth = 1.5 (bur length)</p>
	<p>330 D Bur</p> <p>Connect Pits</p>	<p>Try and maintain 1.5 as much as you can</p> <p>Central groove - more on the lingual side → connect more on facial side so your drilling is more centered</p>
	<p>330 D Bur</p> <p>Make dovetails on both mesial and distal ends</p> <p>Each needs to be parallel to side of the tooth</p>	<p>Just move side to side (facial ←→ lingual) so to not impinge on marginal ridges</p> <p>Make sure to get all of the distal pit (autofail)</p>

	<p>330 D Bur</p> <p>Go into grooves in a <u>rounded way</u> (not sharp)</p>	<p>This gives you your outline form</p>
	<p>330 D Bur</p> <p>Perio probe</p> <p>Make floor level and smooth</p>	<p>Aim for 2.2 mm</p> <p>Need more than 1.5 and less than 3 (auto fails)</p>
	<p>330 D Bur</p> <p>Smooth walls</p>	<p>Center = convergent</p> <p>Ends = divergent or parallel</p> <p>(auto fails)</p>
	<p>Smallest Plugger</p> <p>Check to see if it can pit in all pits</p>	
